#### Its Sew Easy

For this pattern you will need

- 1 1/4 Yard Interior Fabric/Accent Fabric
- 1/4 Yards Exterior Fabric/Top Panel Fabric
- 1 Yard Iron-On Pellon 808 Craft Fuse

Multiple Seam Allowances

Finished Dimensions 10 3/4" x 7 1/4"

- 1.) Prep
  - a. Read all instructions to make sure you understand how the pattern will flow
- 2.) Cut Tie/Strap/Interior/Exterior/Bottom Fabric
  - a. Cut two piece 35 1/2" deep x 2" wide (straps)
  - a. Cut one piece 11 ½" deep x 24" wide (interior)
  - b. Cut one piece 5" deep x 24" wide (exterior accent)
  - c. Cut four pieces 8" circles from template (bottom)
- 3.) Cut Exterior Fabric
  - a. Cut one piece 2" deep x 44" wide or width of fabric (tie)
  - b. Cut one piece 7" deep x 24" wide
- 4.) Cut Stabilizer
  - a. Cut two pieces 11 ½" x 24"
  - b. Cut four 8" circles from template
- 5.) Piece Exterior
  - a. Place exterior fabric on a flat surface with right side up, on top place exterior accent measuring 5" x 24" on top with right side down

- b. Pin along 24" seam. NOTE: When finished 5" exterior accent should be on bottom and 7" exterior piece on top.
- c. Sew using 1/4" seam allowance
- d. Press
- 6.) Attach Stabilizer
  - a. Place one piece of stabilizer measuring 11 ½" x 24" on a flat surface with adhesive side up, on top place exterior panel right side up
  - b. Fuse into place
  - c. Repeat with interior panel and circles
  - d. Edge stitch along exterior seam to reinforce fabric to stabilizer
- 7.) Make Tie and Straps
  - a. Place the tie fabric measuring 2" x 44" on a flat surface
  - b. With the wrong side up fold each 44" edge towards the center 1/2"
  - c. Press in place
  - d. Fold in half so tie now measures 1/2" wide
  - e. Tuck the ½" ends under to hide the raw edge and press in place
  - f. Secure the tie by using an edge stitch
  - g. Repeat with strap fabric measuring 35 ½" deep x 2" wide except no need to tuck ends. NOTE: The raw end edges will be hidden in the seams once the bag is assembled.
- 8.) Create Hidden Interior Pocket
  - a. Place one circle on a flat surface with right side up
  - b. Fold another circle in half with wrong sides together
  - c. Place folded circle on top of circle on flat surface and pin
  - d. Repeat with second circle

- e. Baste using edge stitch to secure
- 9.) Assembling Interior
  - a. Place exterior piece measuring 11 ½" deep x 24" wide on a flat surface with right side up
  - b. Fold in half widthwise with right sides together
  - c. Pin along 11 ½" side
  - d. Sew using 1/4" seam allowance
  - e. Press
  - f. Pin side of bag to bottom circle with right sides together, this will take several pins because of the round bottom
  - g. Sew using 1/4" seam
- 10.) Attaching Straps
  - a. Place exterior piece measuring 11 ½" deep x 24" wide on a flat surface with right side up
  - b. Working on the top right side measure 1  $\frac{1}{4}$ " towards center and pin top of one strap
  - c. Along bottom right side measure 2" towards center and pin bottom of strap
  - d. Baste using edge stitch
  - e. Repeat on left side with second strap. **NOTE: To have a** polished look make sure seams on straps are going in coordinating direction.
- 11.) Assemble Exterior
  - a. Fold exterior panel in half widthwise with right sides together
  - b. Pin along 11 1/2" side
  - c. Sew exterior together using 1/4" seam
  - d. Pin side of bag to bottom circle with right sides together, this will take several pins because of the round bottom

- e. Sew using 1/4" seam while making sure to backstitch on straps
  Assembling Bag
- a. Place exterior inside of interior with right sides together lining up side seams
- b. Pin along top. NOTE: You will need to leave a 4" section unpinned to give you room to flip the bag right sides out, this 4" section should be away from the straps.
- c. Sew around top edge using ½" seam while making sure to reinforce the straps; remembering to leave the 4" section open
- d. Flip bag right side out making sure to line up corresponding interior and exterior bottoms
- e. Finger press the open 4" section of interior and exterior raw edges ½" towards wrong side/stabilizer
- f. Pin to secure
- g. Starting with the 4" pinned section and sew along the top edge of bag using ¼" seam, making sure to reinforce straps, continue around entire top edge
- h. Press

12.)

- 13.) Add Button Holes
  - a. Starting from the top of the side seam measure 1 7/16" to the left and mark
  - b. Continue measuring in 2 15/16" increments seven more times, you will end up with 8 points
  - c. Look to make sure your pins looked evenly spaced and make any minor adjustments

- d. From each mark measure down the bag 2", this will be where you add each buttonhole. NOTE: Use your tie as a buttonhole-sizing guide, this will ensure it is the proper size.
- e. Create 3/4" button holes
- f. Weave tie through buttonholes and pull to secure bag
- g. Steam out any wrinkles
- h. Enjoy!

Calle North gall geston