Learn to

So many designs start with a simple rectangle

Shopping List

- 6 to 8 yards muslin
- 1/4- to 1/2-inch-wide ribbon
- Dress form
- Fabric marker
- Ruler
- Pins
- Scissors

ou don't need a design degree to drape a closet full of unique, wearable fashions. If you own any kind of fairly sturdy dress form with standard markings, all you need to get started with draping are some basic guidelines, a willingness to experiment, and a few yards of inexpensive muslin fabric.

Draping is used by designers (just like those on TV's Project Runway) as a direct, hands-on way to quickly realize a particular garment concept. You can try this method of garment design and, at the same time, create a variety of interesting and pretty skirts. Starting your draping efforts with skirts keeps things simple because there's no bodice or crotch fitting to worry about, and it increases the likelihood of getting wearable results right away.

Draping on a dress form that matches your measurements, or directly on a body, eliminates fitting issues and gives you more time for design play. Once you've learned the basic draping techniques described in this article, you can drape just about any simple design you can imagine and eventually move on to more complicated garment draping.

Adapted from Threads no. 93 "A Skirt Draping Primer" by Theresa LaQuey.




Prep the Dress Form and Fabric

Before draping, you must properly prepare your materials. No matter what kind of dress form you have, it's not ready for a draping project without a few clearly marked reference lines. A cheap, lightweight, loosely woven muslin fabric is perfect for draping because you can easily see the individual threads. Before draping fabric, mark its straight grain or cross-grain; you'll need to first straighten the fabric's grain for accuracy.

MARK THE FORM

Use a narrow, contrasting-color ribbon to mark the dress form at the waistline, center front, center back, and side seams. The waistline marking should follow your natural waistline, while being as horizontal as possible. Make sure the form is firmly supported and oriented as parallel as possible to your own posture. With the form in this position, all vertical lines should be perpendicular to the floor when viewed straight on.


Solid lines on a dress form are required for skirt draping. Pin contrasting ribbon on the form to mark center front, center back, side seams, and waistline.



STRAIGHTEN THE FABRIC GRAIN

Tear enough fabric for your draping project from the **bolt.** You'll need about 3 yards for each of the skirts described in this article. If the starting Selvage ---> edge was cut, snip near the cut and tear across the fabric, from selvage to selvage, so that the Selvage cross-grain edge is raw and parallel to the fabric threads. Sometimes, it's also helpful to tear away (or at least cut) the selvages so that all four fabric edges are raw and can be Tear. corrected easily. Cut edge

Pold the fabric in half with selvages aligned. If the torn edges aren't perfectly parallel, stretch the fabric on the bias to shift the edges in the direction required. Once all the edges match, mark the straight grain or cross-grain (depending on the direction you intend to drape) by pulling a thread near the center of your fabric. To make it more visible, trace the pulled thread with a marker. When you begin draping, this marked grainline is aligned with the center-front or center-back markings on the dress form.



Fold the torn fabric in half with its selvages aligned. To correct the grain, stretch the fabric in the direction opposite to the distortion.

Start with a Hip Yoke

It's much easier to drape a skirt from the bottom seam of a hip yoke than over the curves at the waistline and hip. Here, you'll learn to drape a contoured, non-darted hip yoke that fits perfectly. Always start draping at the center front or center back and work toward the sides. As you drape, make sure that the marked grainline on the fabric remains straight. You need to drape only half of a symmetrical design.


Begin draping the front. Start with a straight-grained muslin rectangle several inches wider on each side than your form measures from side seam to side seam. Mark the center front at the pulled thread marking. Center the rectangle over the form's waist and centerfront marks, pin it there to secure it to the form, and loosely pin the sides to hold it in place.



2 Shape the waist.
Smooth the muslin toward one side seam without distorting the center-front grain. Repin at the side seam to hold the muslin precisely. Trace the waistline tape, center-front, and sideseam positions onto the muslin.




Oetermine the yoke **depth.** Measure down from the waist tape about 4 inches to 5 inches and mark the yoke's depth evenly from side seam to center front. To ensure the voke lies smoothly, its bottom edge shouldn't sit lower than the top of any loose folds that form in the lower part of the muslin The depth may need adjusting after you've draped the back yoke.



4 Drape the back yoke. With a second rectangle of fabric, repeat steps 1 to 3 on the back of the form. If the back yoke is deeper or shallower than the front, adjust the front to match.



True the draped yoke. Unpin the muslins and correct the seamlines to ensure they match and curve smoothly. Mark notches for matching on the seamlines. Add at least ½-inchwide seam allowances to all seams except center front. Mark the center-front line "Place on fold." (The back yoke receives a zipper at center back.) Cut out the draped and trued front and back yoke sections from the muslin, including the added seam allowances.



Go back to the form. Pin the completed yoke in place on the form. Now you're ready to drape the rest of the skirt.




52 sewstylish ■ SewStylish.com
FALL 2013 53



Drape a Straight Skirt

If the lower skirt section's hip seamline is straight, then the skirt will fall flat against the body, without fullness. However, you can adjust the straight skirt's fullness to provide wearing ease or give the proper fit over fuller thighs.

Prepare the fabric. Tear a muslin rectangle several inches longer than your desired skirt length and wider than one-quarter the total hip circumference. Straighten and mark the grain at center front, running lengthwise on the muslin rectangle.




1 Establish the length. Mark the side **)** seam and center front and extend them to the desired skirt length.


Add fullness for ease. If you prefer or need more ease through the thigh, raise the skirt's hipline seam slightly at center front and center back. This creates a deeper curve at the seam and adds barely noticeable fullness that prevents the skirt from clinging. You can use this technique to add precise amounts of fullness to a straight draped skirt to suit your comfort level.

Web EXTRA

For details on how to transfer a muslin drape to pattern paper, visit SewStylish.com.

Orape the skirt front. Align the muslin's marked center front to the dress form's center front, overlapping the yoke's bottom seamline, allowing a ¹/₂-inch-wide seam allowance, and pin. As you hold the grainline at center front perpendicular to the floor, smooth the muslin toward the side seam and pin it in place. Repeat the process for the skirt





Drape an Angled-Hipline Skirt

If the lower skirt's hip seamline has an angle cut into it, the skirt will fall with all fullness directly below the angle when it is sewn to the yoke. This shape creates fullness in the skirt only at the point of the angle, which is halfway between center front/center back and the side seam. There are two hem options with this style, each giving a completely different finished look: a curved hem or a square handkerchief hem. Remember, you only need to drape half of the skirt front and half of the skirt back.

Cut the skirt's Hip seamline **Center front** hip seamline. Start with two squares of fabric Measure onetorn 5 inches to half length 8 inches longer than of the hip the desired skirt Cut away length. Shape the the square. angled hip seamline by measuring in Side —> from one corner seam on both sides half the length of the hip seamline from Handkerchief hem the center front

or center back to the side seam. Cut away the resulting square. The skirt's hipline seam must extend around the hipline when clipped from the center front or center back to the side seam with enough excess for 1/2-inch-wide seam allowances all around.

Orape the skirt. On the front and the back, start by overlapping and pinning one half of the skirt's angled hip seamline over the yoke's hip seamline at center front or center back. Smooth the skirt's hip seamline, clipping if necessary, along the yoke to the side seam. Mark the hip seamline, center front or back, and side-seam points. At the form's side seams, mark the skirt side seams by following the muslin's thread straight down to the desired hem.

Shape the Hip seamline **hem.** You can leave the hem square to create handkerchief points in the front and back directly below the hipline angle (as shown on page 51), or you can create a curved hem (shown at right). To mark a **Curved hem** curved hemline, use a hem marker

or measure from the floor to the desired length, with the skirt on the dress form.

